
MatrixSSL Developer's Guide

MatrixSSL 3.3



Minutiae
047 018 287
106 021 192
070 023 210
053 024 000
073 032 230
108 032 428
091 033 174
058 039 248
108 054 402
125 059 400
099 060 400
070 061 256
048 068 340
065 070 338
104 071 358
115 075 358
041 077 096
123 079 384
063 083 064
053 091 052
028 097 052
084 100 031
050 102 044
103 106 050
117 111 046
104 118 282

Software Manual

3128 Rev 1
23 01 12

AuthenTec, Inc.
100 Rialto Place, Suite 100
Melbourne, Florida 32901
321.308.1300
authentec . com

AuthenTec welcomes your input. We try to make our publications useful, interesting, and informative, and we hope you will take the time to help us improve them. Please send any comments or suggestions by mail or e-mail.

Disclaimer of Warranty

AUTHENTEC SOFTWARE, INCLUDING INSTRUCTIONS FOR ITS USE, IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND. AUTHENTEC FURTHER DISCLAIMS ALL IMPLIED WARRANTIES INCLUDING WITHOUT LIMITATION ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR OF FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK ARISING OUT OF THE USE OR PERFORMANCE OF THE SOFTWARE AND DOCUMENTATION REMAINS WITH YOU.

IN NO EVENT SHALL AUTHENTEC, ITS AUTHORS, OR ANYONE ELSE INVOLVED IN THE CREATION, PRODUCTION, OR DELIVERY OF THE SOFTWARE BE LIABLE FOR ANY DAMAGES WHATSOEVER (INCLUDING, WITHOUT LIMITATION, DAMAGE FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF BUSINESS INFORMATION, OR OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR INABILITY TO USE THE SOFTWARE OR DOCUMENTATION, EVEN IF AUTHENTEC HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. BECAUSE SOME STATES OR COUNTRIES DO NOT ALLOW THE EXCLUSION OR LIMITATION OF LIABILITY FOR CONSEQUENTIAL OR INCIDENTAL DAMAGES, THE ABOVE LIMITATION MAY NOT APPLY TO YOU.

U.S. Government Restricted Rights

AuthenTec software and documentation are provided with RESTRICTED RIGHTS. Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 or subparagraph (c)(1) and (2) of the Commercial Computer Software – Restricted Rights 48 CFR 52.227-19, as applicable. Manufacturer is AuthenTec, Inc., Melbourne, Florida 32901. This Agreement is governed by the laws of the State of Florida.

AuthenTec, Inc.
100 Rialto Place, Suite 100
Melbourne, Florida 32901
321-308-1300
www.authentec.com
apps@authentec.com

MatrixSSL Developer's Guide **3128 Rev 1 (23 01 12)**

The material in this publication is provided for information only. It is subject to change without notice. While reasonable efforts have been made to assure its accuracy, AuthenTec, Inc. assumes no liability resulting from errors or omissions in the document, or from the use of the information contained herein.

Copyright © 2012 by AuthenTec, Inc. All rights reserved. No part of this publication may be reproduced in any form or by any means without prior written permission. Printed in the United States of America.

Table of Contents

TABLE OF CONTENTS	2
OVERVIEW	3
COMMERCIAL VERSION DIFFERENCES	3
SECURITY CONSIDERATIONS	3
SSL vs. TLS	3
SELECTING CIPHER SUITES	3
AUTHENTICATION MODE	4
CERTIFICATES AND PRIVATE KEYS	5
APPLICATION INTEGRATION FLOW	6
SSL_T STRUCTURE	6
INITIALIZATION	6
CREATING A SESSION	7
HANDSHAKING	7
COMMUNICATING SECURELY WITH PEERS	9
ENCRYPTING DATA	9
DECRYPTING DATA	10
ENDING A SESSION	10
CLOSING THE LIBRARY	10
CONFIGURABLE FEATURES	11
PROTOCOL AND PERFORMANCE	11
DEBUG CONFIGURATION	12
SSL HANDSHAKING	13
STANDARD HANDSHAKE	13
CLIENT AUTHENTICATION	14
SESSION RESUMPTION	15
RE-HANDSHAKES	15

Overview

This developer's guide is a general SSL/TLS overview and a MatrixSSL specific integration reference for adding SSL security into an application.

This document is primarily intended for the software developer performing a MatrixSSL integration into their custom application but is also a useful reference for anybody wishing to learn more about MatrixSSL or the SSL/TLS protocol in general.

For additional information on the APIs discussed here please see the [MatrixSSL API](#) document included in this package.

Commercial Version Differences

Some of the compile options, functions, and structures in this document provide additional features only available in the commercially licensed version of MatrixSSL. Sections of this document that refer to the commercial version will be shaded as this paragraph has.

Functionality and features that are available exclusively in the commercial version may not be included in this documentation package. Below is a partial list of topics available in the full MatrixSSL documentation library.

- Diffie-Hellman Cipher Suites
- Pre-Shared Key Cipher Suites
- Deterministic Memory

Security Considerations

Prior to working directly with the MatrixSSL library there are a couple SSL security concepts that application integrators should be familiar with.

SSL vs. TLS

MatrixSSL supports both the TLS and SSL protocols. Despite the difference in acronym, TLS 1.0 is simply version 3.1 of SSL. There are no practical security differences between the protocols, and only minor differences in how they are implemented. It was felt that 'Transport Layer Security' was a more appropriate name than 'Secure Sockets Layer' going forward beyond SSL 3.0. In this documentation, the term SSL is used generically to mean SSL/TLS, and TLS is used to indicate specifically the TLS protocol. MatrixSSL supports the TLS 1.1 protocol as well.

Selecting Cipher Suites

The strength (and thus performance) of the secure communications are primarily determined by the choice of cipher suites that will be supported. A cipher suite determines how two peers progress through an SSL handshake as well as how the final application data will be encrypted over the secure connection. The four components of any given cipher suite are **key exchange, authentication, encryption and digest hash**.

Key exchange mechanisms refer to how the peers agree upon a common symmetric key that will be used to encrypt data after handshaking is complete. The two common key exchange algorithms are RSA and Diffie-Hellman (DH). Currently, when Diffie-Hellman is chosen it is used almost exclusively in ephemeral mode (DHE) in which new private key pairs are generated for each connection to allow perfect forward secrecy. The tradeoff for DHE is a much slower SSL handshake as key generation is a relatively processor-intensive operation. Some older protocols also specify DH, as it was the first widely publicized key exchange algorithm.

The authentication algorithm specifies how the peers will prove their identities to each other. Authentication options within cipher suites are RSA, DSA, Elliptic Curve DSA (ECDSA), Pre-shared Key (PSK), or anonymous if no authentication is required. RSA has the unique property that it can be used for both key exchange and authentication. For this reason, RSA has become the most widely implemented cipher suite mechanism for SSL communications. RSA key strengths of between 1024 and 2048 bits are the most common.

The encryption component of the cipher suite identifies which symmetric cipher is to be used when exchanging data at the completion of the handshake. The AES block cipher is recommended for new implementations, and is the most likely to have hardware acceleration support.

Finally, the digest hash is the choice of checksum algorithm used to confirm the integrity of exchanged data, with SHA-1 being the most common. Here is a selection of cipher suites that illustrate how to identify the four components.

Cipher Suite	Key Exchange	Auth Type	Encryption	Digest Hash
SSL_RSA_WITH_3DES_EDE_CBC_SHA	RSA	RSA	3DES	SHA-1
SSL_DH_anon_WITH_RC4_128_MD5	DH	anonymous	RC4-128	MD5
TLS_RSA_WITH_AES_128_CBC_SHA	RSA	RSA	AES-128	SHA-1
TLS_DHE_RSA_WITH_AES_256_CBC_SHA	DHE	RSA	AES-256	SHA-1
TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA	ECDHE	RSA	AES-128	SHA-1
TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA	ECDHE	ECDSA	AES-256	SHA-1

Authentication Mode

By default in SSL, it is the server that is authenticated by a client. It is easiest to remember this when thinking about purchasing a product online with a credit card over an HTTPS (SSL) connection. The client Web browser must authenticate the server in order to be confident the credit card information is being sent to a trusted source. This is referred to as one-way authentication or server authentication and is performed as part of all standard SSL

connections (unless, of course, a cipher suite with an authentication type of anonymous has been agreed upon).

However, in some use-case scenarios the user may require that both peers authenticate each other. This is referred to as mutual authentication or client authentication. If the project requires client authentication there is an additional set of key material that must be used to support it.

Certificates and Private Keys

With a cipher suite and authentication mode chosen, the user will need to obtain or generate the necessary key material for supporting the authentication and key exchange mechanisms. X.509 is the standard for how key material is stored in **certificate files**.

The peer that is being authenticated must have a private key and a public certificate. The peer performing the authentication must have the Certificate Authority (CA) certificate that was used to issue the public certificate. In the standard one-way authentication scenario this means the server will load a private key and certificate while the client will load the CA file.

If client authentication is needed the mirror image of CA, certificate, and private key files must also be used. This chart shows which files are needed by clients and servers that are using a standard RSA based cipher suite such as `SSL_RSA_WITH_3DES_EDE_CBC_SHA`.

Authentication Mode	Server Key Files	Client Key Files
One-way server authentication	<ol style="list-style-type: none"> 1. RSA server certificate file 2. RSA private key file for the server certificate file 	<ol style="list-style-type: none"> 1. Certificate Authority certificate file that issued the server certificate
Additional for client authentication	<ol style="list-style-type: none"> 3. Certificate Authority certificate file that issued the client certificate 	<ol style="list-style-type: none"> 2. RSA client certificate file 3. RSA private key file for the client certificate file

For information on how to create Certificate Authority root and child certificates please see the [Matrix Key Generation Utilities](#) document.

Application Integration Flow

MatrixSSL is a C code library that provides a security layer for client and server applications allowing them to securely communicate with other SSL enabled peers. MatrixSSL is transport agnostic and can just as easily integrate with an HTTP server as it could with a device communicating through a serial port. For simplicity, this developer's guide will assume a socket-based implementation for all its examples unless otherwise noted.

The term *application* in this document refers to the peer (client or server) application the MatrixSSL library is being integrated into.

This section will detail the specific points in the application life cycle where MatrixSSL should be integrated. In general, MatrixSSL APIs are used for initialization/cleanup, when new secure connections are being established (handshaking), and when encrypting/decrypting messages exchanged with peers.

Refer to the MatrixSSL API document to get familiar with the interface to the library and with the example code to see how they are used at implementation. Follow the guidelines below when using these APIs to integrate MatrixSSL into an application.

ssl_t Structure

The `ssl_t` structure holds the state and keys for each client or server connection as well as buffers for encoding and decoding SSL data. The buffers are dynamically managed internally to make the integration with existing non-secure software easier. SSL is a record based protocol, and the internal buffer management makes a better "impedance match" with classic stream based protocols. For example, data may be read from a socket, but if a full SSL record has not been received, no data is available for the caller to process. This partial record is held within the `ssl_t` buffer. The MatrixSSL API is also designed so there are no buffer copies, and the caller is able to read and write network data directly into the SSL buffers, providing a very low memory overhead per session.

Initialization

MatrixSSL must be initialized as part of the application initialization with a call to `matrixSslOpen`. This function takes no parameters and sets up the internal structures needed by the library.

In most cases, the application will subsequently load the key material from the file system. RSA certificates, Diffie-Hellman parameters, and Pre-Shared Keys for the specific peer application must be parsed before creating a new SSL session. The `matrixSslNewKeys` function is used to allocate the key storage and `matrixSslLoadRsaKeys`, `matrixSslLoadDhParams`, and `matrixSslLoadPsk` are used to parse the key material into the `sslKeys_t` structure during initialization. The populated key structure will be used as an input parameter to `matrixSslNewClientSession` or `matrixSslNewServerSession`.

The allocation and loading of the `sslKeys_t` structure is most commonly done a single time at start and the application uses those keys for each connection. Alternatively, a new `sslKeys_t` structure can be allocated once for each secure connection and freed immediately after the connection is closed. This should be done if the application has multiple certificate

files depending on the identity of the connecting entity or if there is a security concern with keeping the RSA keys in memory for extended periods of time.

Once the application is done with the keys, the associated memory is freed with a call to `matrixSslFreeKeys`.

Creating a Session

The next MatrixSSL integration point in the application is when a new session is starting. In the case of a client, this is whenever it chooses to begin one, because SSL is a client-initiated protocol (like HTTP). In the case of a server, a new session should be started when the server accepts an incoming connection from a client. In a socket based application, this would typically happen when the `accept` socket call returns with a valid incoming socket. The application sets up a new session with the API `matrixSslNewClientSession` or `matrixSslNewServerSession`. The returned `ssl_t` context will become the input parameter for all public APIs that act at a per-session level.

The required input parameters to the session creation APIs differ based on whether the application is assuming a server or client role. Both require a populated keys structure (discussed in the previous section) but a client can also nominate a specific cipher suite or session ID when starting a session. The ciphers that the server will accept are determined at compile time.

The client should also always nominate a certificate callback function during `matrixSslNewClientSession`. This callback function will be invoked mid-handshake to allow the user to inspect the key material, date and other certificate information sent from the server. For detailed information on this callback function, see the API documentation for `matrixSslNewClientSession`.

In the commercial version the server may also choose to nominate a certificate callback function if client authentication is desired. The MatrixSSL library must have been compiled with `USE_CLIENT_AUTH` defined in order to use this parameter.

For clients wishing to quickly (and securely) reconnect to a server that it has recently connected to, there is an optional `sessionId` parameter that may be used to initiate a faster resumed handshake (the cpu intensive public key exchange is omitted). To use the session parameter, a client should allocate a `sslSessionId_t` structure, initialize it with `matrixSslInitSessionId` and pass its pointer to `matrixSslNewClientSession` during the initial connection with the server. Over the course of the session negotiation, the MatrixSSL library will populate that structure behind-the-scenes so that during the next connection the same `sessionId` parameter address can be used to initiate the resumed session.

Handshaking

During client session initialization with `matrixSslNewClientSession` the SSL handshake message `CLIENT_HELLO` is encoded to the internal outgoing buffer. The client now needs to send this message to the server over a communication channel.

The sequence of events that should always be used to transmit pending handshake data is as follows:

1. The user calls `matrixSslGetOutdata` to retrieve the encoded data and number of bytes to be sent
2. The user sends the # of bytes indicated from the out data buffer pointer to the peer
3. The user calls `matrixSslSentData` with the actual number of bytes that were sent
4. If more data remains (bytes sent < bytes to be sent), repeat the above 3 steps when transport layer is ready to send again

When the server receives notice that a client is starting a new session the `matrixSslNewServerSession` API is invoked and the incoming data is retrieved and processed.

The sequence of events that should always be used when expecting handshake data from a peer is as follows:

1. The application calls `matrixSslGetReadbuf` to retrieve a pointer to available buffer space in the `ssl_t` structure.
2. The application reads incoming data into that buffer
3. The application calls `matrixSslReceivedData` to process the data
4. The application examines the return code from `matrixSslReceivedData` to determine the next step

All incoming messages should be copied into the provided buffer and passed to `matrixSslReceivedData`, which processes the message and drives the handshake through the built-in SSLv3 or TLS state machine. The parameters include the SSL context and the number of bytes that have been received. Its return code tells the application what the message was and how it is to be handled:

MATRIXSSL_REQUEST_SEND	Success. The processing of the received data resulted in internal creation of an SSL response message that needs to be sent to the peer. If this return code is hit the user should call <code>matrixSslGetOutdata</code> to retrieve the encoded outgoing data and send it.
MATRIXSSL_REQUEST_RECV	Success. More data must be received and this function must be called again. Most likely a partial record was read and more data is required to continue parsing. User must call <code>matrixSslGetReadBuf</code> again to receive the updated buffer pointer and length to where the remaining data should be read into.

MATRIXSSL_HANDSHAKE_COMPLETE	Success. The SSL handshake is complete. This return code is returned to client side implementation during a full handshake after parsing the FINISHED message from the server. It is possible for a server to receive this value if a resumed handshake is being performed where the client sends the final FINISHED message. Client applications will typically use this state as a trigger to send a client initiated protocol message (such as HTTP GET).
MATRIXSSL_RECEIVED_ALERT	Success. The data that was processed was an SSL alert message. In this case, the plaintext pointer will be two bytes (ptLen will be 2) in which the first byte will be the alert level and the second byte will be the alert description. After examining the alert, the user must call <code>matrixSslProcessedData</code> to indicate the alert was processed and the data may be internally discarded.
MATRIXSSL_APP_DATA	Success. The data that was processed was application data that the user should process. In this return code case the plaintext and ptLen output parameters will be valid. The user must process the all the data directly from <code>plainText</code> or copy it aside for later processing. After handling the data the user must call <code>matrixSslProcessedData</code> to indicate the <code>plainText</code> data may be internally discarded.
< 0	Failure. See API documentation for more information

Communicating Securely With Peers

Encrypting Data

Once the handshake is complete, the application wishing to encrypt data that will be sent to the peer has the choice between two encoding options.

In-Situ Encryption

An in-situ encryption occurs when the outputted cipher text overwrites the plain text during the encoding process. In this case, the user will retrieve an allocated buffer from the MatrixSSL library, populate the buffer with the desired plaintext, and then notify the library that the plaintext is ready to be encoded. The API steps for the in-situ method are as follows:

1. The application first determines the length of the plaintext that needs to be sent
2. The application calls `matrixSslGetWritebuf` with that length to retrieve a pointer to an internally allocated buffer.
3. The application writes the plaintext into the buffer and then calls `matrixSslEncodeWritebuf` to encrypt the plaintext

4. The application calls `matrixSslGetOutdata` to retrieve the encoded data and length to be sent (SSL always adds some overhead to the message size)
5. The application sends the out data buffer contents to the peer.
6. The application calls `matrixSslSentData` with the # of bytes that were actually sent

User provided plaintext data location

The alternative to in-situ encryption is to allow the user to provide the location and length of the plaintext data that needs to be encoded. In this case, the encrypted data is still written to the internal MatrixSSL outdata buffer but the user provided plaintext data is left untouched. The API steps for this method are as follows:

1. The user passes the plaintext and length to `matrixSslEncodeToOutdata`
2. The application calls `matrixSslGetOutdata` to retrieve the encoded data and length to be sent (SSL always adds some overhead to the message size)
3. The application sends the out data buffer contents to the peer.
4. The application calls `matrixSslSentData` with the # of bytes that were actually sent

Decrypting Data

The sequence of events that should always be used when expecting application data from a peer is as follows:

1. The application calls `matrixSslGetReadbuf` to retrieve an allocated buffer
2. The application copies the incoming data into that buffer
3. The application calls `matrixSslReceivedData` to process the data
4. The application confirms the return code from `matrixSslReceivedData` is `MATRIXSSL_APP_DATA` and parses `ptLen` bytes of the returned `plainText`
5. If the return code does not indicate application data, handle the return code as described in the handshaking section above.
6. The application calls `matrixSslProcessedData` to inform the library it is finished with the plaintext and checks to see if there are additional records in the buffer to process.

Ending a Session

When the application receives notice that the session is complete or has determined itself that the session is complete, it should notify the other side, close the socket and delete the session. Calling `matrixSslEncodeClosureAlert` and `matrixSslDeleteSession` will perform this step.

A call to `matrixSslEncodeClosureAlert` is an optional step that will encode an alert message to pass along to the other side to inform them to close the session cleanly. The closure alert buffer is retrieved and sent using the same `matrixSslGetOutdata/matrixSslSentData` mechanism that all outgoing data uses. Since the connection is being closed, the application shouldn't block indefinitely on sending the closure alert.

Closing the Library

At application exit the MatrixSSL library should be un-initialized with a call to `matrixSslClose`. If the application has called `matrixSslNewKeys` as part of the initialization process and kept its keys in memory it should call `matrixSslDeleteKeys` before calling

`matrixSslClose`. Also, any existing SSL sessions should be freed by calling `matrixSslDeleteSession` before calling `matrixSslClose`.

Working implementations of MatrixSSL client and server applications integration can be found in the *apps* subdirectory of the distribution package.

Configurable Features

MatrixSSL contains a set of optional features that are configurable at compile time. This allows the user to remove unneeded functionality to reduce code size footprint. Each of these options are pre-processor defines that can be disabled by simply commenting out the `#define` in the header files or by using the `-D` compile flag during build. APIs with dependencies on optional features are highlighted in the **Define Dependencies** sub-section in the API documentation for that function.

Protocol and performance

MATRIX_USE_FILE_SYSTEM	Define in the build environment. Enables file access for parsing X.509 certificates and private keys.
USE_CLIENT_SIDE_SSL	<i>matrixsslConfig.h</i> - Enables client side SSL support
USE_SERVER_SIDE_SSL	<i>matrixsslConfig.h</i> - Enables server side SSL support
USE_TLS	<i>matrixsslConfig.h</i> - Enables TLS 1.0 protocol support (SSL version 3.1)
USE_TLS_1_1	<i>matrixsslConfig.h</i> - Enables TLS 1.1 (SSL version 3.2) protocol support. USE_TLS must be enabled
DISABLE_SSLV3	<i>matrixsslConfig.h</i> - Disables SSL version 3.0
ENABLE_SECURE_REHANDSHAKES	<i>matrixsslConfig.h</i> - Enable secure rehandshaking as defined in RFC 5746
REQUIRE_SECURE_REHANDSHAKES	<i>matrixsslConfig.h</i> - Halt communications with any SSL peer that has not implemented RFC 5746
ENABLE_INSECURE_REHANDSHAKES	<i>matrixsslConfig.h</i> - Enable legacy renegotiations. NOT RECOMMENDED

USE_CLIENT_AUTH	<i>matrixsslConfig.h</i> - Enables two-way(mutual) authentication
SERVER_CAN_SEND_EMPTY_CERT_REQUEST	<i>matrixsslConfig.h</i> – A client authentication feature. Allows the server to send an empty CertificateRequest message if no CA files have been loaded
SERVER_WILL_ACCEPT_EMPTY_CLIENT_CERT_MSG	<i>matrixsslConfig.h</i> – A client authentication feature. Allows the server to ‘downgrade’ a client auth handshake to a standard handshake if client does not provide a certificate
USE_PRIVATE_KEY_PARSING	<i>cryptoConfig.h</i> - Enables X.509 private key parsing
USE_PKCS5	<i>cryptoConfig.h</i> - Enables the parsing of password protected private keys
USE_PKCS8	<i>cryptoConfig.h</i> - Enables the parsing of PKCS#8 formatted private keys
USE_PKCS12	<i>cryptoConfig.h</i> - Enables the parsing of PKCS#12 formatted certificate and key material
USE_1024_KEY_SPEED_OPTIMIZATIONS	<i>cryptoConfig.h</i> - Enables fast math for 1024-bit public key operations
PS_PUBKEY_OPTIMIZE_FOR_SMALLER_RAM PS_PUBKEY_OPTIMIZE_FOR_FASTER_SPEED	<i>cryptoConfig.h</i> - RSA and Diffie-Hellman speed vs. runtime memory tradeoff. Default is to optimize for smaller RAM.
PS_AES_IMPROVE_PERF_INCREASE_CODESIZE PS_3DES_IMPROVE_PERF_INCREASE_CODESIZE PS_MD5_IMPROVE_PERF_INCREASE_CODESIZE PS_SHA1_IMPROVE_PERF_INCREASE_CODESIZE	<i>cryptoConfig.h</i> - Optionally enable for selected algorithms to improve performance at the cost of increased binary code size.

Debug Configuration

MatrixSSL contains a set of optional debug features that are configurable at compile time. Each of these options are pre-processor defines that can be disabled by simply commenting out the #define in the specified header files.

HALT_ON_PS_ERROR	<i>coreConfig.h</i> - Enables the osdepBreak platform function whenever a _psError trace function is called. Helpful in debug environments.
USE_CORE_TRACE	<i>coreConfig.h</i> - Enables the psTraceCore family of APIs that display function-level messages in the core module
USE_CRYPTO_TRACE	<i>cryptoConfig.h</i> - Enables the psTraceCrypto family of APIs that display function-level messages in the crypto module
USE_SSL_HANDSHAKE_MSG_TRACE	<i>matrixsslConfig.h</i> - Enables SSL handshake level debug trace for troubleshooting connection problems
USE_SSL_INFORMATIONAL_TRACE	<i>matrixsslConfig.h</i> - Enables SSL function level debug trace for troubleshooting connection problems

SSL Handshaking

The core of SSL security is the handshake protocol that allows two peers to authenticate and negotiate symmetric encryption keys. A handshake is defined by the specific sequence of SSL messages that are exchanged between the client and server. A collection of messages being sent from one peer to another is called a **flight**.

Standard Handshake

The standard handshake is the most common and allows a client to authenticate a server. There are four flights in the standard handshake.

CLIENT	SERVER
----- CLIENT_HELLO ----->	
	<----- SERVER_HELLO -----
	<----- CERTIFICATE -----
	<----- SERVER_HELLO_DONE -----
----- CLIENT_KEY_EXCHANGE ----->	
----- CHANGE_CIPHER_SPEC ----->	
----- FINISHED ----->	
	<----- CHANGE_CIPHER_SPEC -----
	<----- FINISHED -----


Client Notes

The client is the first to send and the last to receive. Therefore, a MatrixSSL implementation of a client must be testing for the MATRIXSSL_HANDSHAKE_COMPLETE return code from `matrixSslReceivedData` to determine when application data is ready to be encrypted and sent to the server.

When a client wishes to begin a standard handshake, `matrixSslNewClientSession` will be called with an empty `sessionId`, initialized with `matrixSslInitSessionId`.

Client Authentication

The client authentication handshake allows a two-way authentication. There are four flights in the client authentication handshake.

**Client Notes**

The client is the first to send and the last to receive. Therefore, a MatrixSSL implementation of a client must be testing for the MATRIXSSL_HANDSHAKE_COMPLETE return code from `matrixSslReceivedData` to determine when application data is ready to be encrypted and sent to the server.


In order to participate in a client authentication handshake, the client must have loaded a Certificate Authority file during the call to `matrixSslLoadRsaKeys`.

Server Notes

To prepare for a client authentication handshake the server must nominate a certificate and private key during the call to `matrixSslLoadRsaKeys`. The actual determination of whether or not to perform a client authentication handshake is made when nominating a certificate callback parameter when invoking `matrixSslNewServerSession`. If the callback is provided, a client authentication handshake will be requested.

Session Resumption

Session resumption enables a previously connected client to quickly resume a session with a server. Session resumption is much faster than other handshake types because public key authentication is not performed (authentication is implicit since both sides will be using secret information from the previous connection). This handshake type has three flights.



Client Notes

The client is the first and the last to send data. Therefore, a MatrixSSL implementation of a client must be testing for the `MATRIXSSL_HANDSHAKE_COMPLETE` return code from `matrixSslSentData` to determine when application data is ready to be encrypted and sent to the server.

The client initiates a session resumption handshake by reusing the same `sessionId_t` structure from a previously connected session when calling `matrixSslNewClientSession`.

Server Notes

The MatrixSSL server will cache a `SSL_SESSION_TABLE_SIZE` number of session IDs for resumption. The length of time a session ID will remain in the case is determined by `SSL_SESSION_ENTRY_LIFE`.

Re-Handshakes

A re-handshake is a handshake over a currently connected SSL session. A re-handshake may take the form of a standard handshake, a client authentication handshake, or a resumed handshake. Either the client or server may initiate a re-handshake.

The `matrixSslEncodeRehandshake` API is used to initiate a re-handshake. The three most common reasons for initiating re-handshakes are:

Re-key the symmetric cryptographic material

Re-keying the symmetric keys adds an extra level of security for applications that require the connection be open for long periods of time or transferring large amounts of data. Periodic changes to the keys can discourage hackers who are mounting timing attacks on a connection.

Perform a client authentication handshake

A scenario may arise in which the server requires that the data being exchanged is only allowed for a client whose certificate has been authenticated, but the original negotiation took place without client authentication. In order to do a client authenticated re-handshake the server must call `matrixSslEncodeRehandshake` with a certificate callback parameter.

Change cipher spec

The cipher suite may be changed on a connected session using a re-handshake if needed. The client must call *matrixSslEncodeRehandshake* with the new cipherSpec.



AuthenTec, Inc.
100 Rialto Place, Suite 100
Melbourne, Florida 32901
321-308-1300 (voice)
321-308-1430 (fax)
www.authentec.com
apps@authentec.com